

## Structure Data Dictionary

This document describes the Structure dataset in the Colorado Information Marketplace.

### Data Dictionary

Field Name	Description
WDID	Unique Structure identifier.
Structure type	Type of Structure.
Structure name	Structure name.
Current-in-use code	The current physical status of the structure and whether diversion records are currently being tracked.
Water Source	Water Source where the Structure is located.
Water Source mile	Number of miles from Confluence or State Line that structure is located.
Associated Permits	Listing of well permits associated with the structure.
Associated Case Numbers	Listing of Water Court case numbers associated with the structure.
Decreed Rate abs	Based on a summation of current water rights, the maximum rate (CFS) of Absolute rights appropriated.
Decreed Rate cond	Based on a summation of current water rights, the maximum rate (CFS) of Conditional rights appropriated.
Decreed Rate APEX abs	Based on a summation of current water rights, the maximum rate (CFS) of Absolute Alternate Point and Exchange rights appropriated.
Decreed Rate APEX cond	Based on a summation of current water rights, the maximum rate (CFS) of Conditional Alternate Point and Exchange rights appropriated.
Decreed Volume abs	Based on a summation of current water rights, the maximum volume (AF) of Absolute rights appropriated.
Decreed Volume cond	Based on a summation of current water rights, the maximum volume (AF) of Conditional rights appropriated.
Decreed Volume APEX abs	Based on a summation of current water rights, the maximum rate (CFS) of Absolute Alternate Point and Exchange rights appropriated.
Decreed Volume APEX cond	Based on a summation of current water rights, the maximum rate (CFS) of Conditional Alternate Point and Exchange rights appropriated.
DIV	Division where the Structure is located.
WD	Water District where the Structure is located.

County	County where the Structure is located.
PM	Principle Meridian.
Township	Township
Range	Range
Section	Section
Q160	160 acre quarter section indicator.
Q40	40 acre quarter section indicator.
Q10	10 acre quarter section indicator.
CoordsEW	Distance from east/west section line (feet).
CoordsEW dir	Direction of measurement from east/west section line.
CoordsNS	Distance from north/south section line (feet).
CoordsNS dir	Direction of measurement from north/south section line.
UTM x	The x (Easting) component of the Universal Transverse Mercator system. (NAD83 datum)
UTM y	The y (Northing) component of the Universal Transverse Mercator system. (NAD83 datum)
Location Accuracy	Accuracy of UTM coordinates.
Diversion Record Start	First year that daily and/or infrequent Diversion Records are available for the Structure.
Diversion Record End	Last year that daily and/or infrequent Diversion Records are available for the Structure.
More Information	Hyperlink to more information about the Structure.
Location	Latitude/Longitude where the Structure is located.